



Mail App (Mac)

Prepare the following pieces of information in advance.

These wares displayed on screen when you subscribed. You will also find those on the Access Information Sheet that was sent to you.


In the following description which are shown in **green**, please replace it with your own details.

Name	Value
Mail password	
Mail address	xxx99999@xxxxx.att.ne.jp

I guide you about "Mail 14" with this manual.


When you have you confirm existing setting, look from Step6.

Step1. Launch "Mail" on Dock.




Step2. Click "Mail" > "Add Account" on the menu bar.

When you see the Add Account window, go to Step3.



Step3. Select " Other Mail Account" and click "Continue".




Choose a Mail account provider...

- iCloud
- Microsoft Exchange
- Google™
- yahoo!
- Aol.
- Other Mail Account...

? Quit Continue

Step4. Select " Other Mail Account" and click "Continue".



@ Add a Mail account

To get started, fill out the following information:

Name: SpinNet_Support

Email Address: xxx99999@xxxxx.att.ne.jp

Password: ●●●●●●●●

Cancel Back Sign In


Name	Value
Name	You first and last name (not necessary)
Email Address	Your mail address. e.g. xxx99999@xxxxx.att.ne.jp
Password	Your mail password

Step5. An error is output.
Enter the following, and click "Sign In".


The screenshot shows a web form for configuring an email account. The fields are filled with placeholder text: 'xxx99999@xxxxx.att.ne.jp' for both Email Address and User Name, and a masked password of ten dots. The Account Type is set to 'POP'. Incoming Mail Server is 'popssl.att.ne.jp' and Outgoing Mail Server is 'smtpssl.att.ne.jp'. A red error message 'Unable to verify account name or password.' is displayed below the server fields. At the bottom are three buttons: 'Cancel', 'Back', and 'Sign In'.

Name	Value
Email Address	Your mail address e.g. xxx99999@xxxxx.att.ne.jp
User Name	Your mail address
Password	Your mail password
Account Type	POP
Incoming Mail Server	popssl.att.ne.jp
Outgoing Mail Server	smtpssl.att.ne.jp

Step6. Click "Mail" > "Preferences" on the menu bar.




- Step7.**
- ① Click “Accounts”.
 - ② Click ”Account” on the left menu.
 - ③ Click “Account Information” and check the following.




Name	Value
Description	e.g. SpinNet_Account
Remove copy from server after retrieving a message	Confirm it is checked.

Step8. Click "Server Settings".



Step9. Uncheck both "Automatically manage connection settings" for the incoming mail server (POP) and outgoing mail server (SMTP).



Step10. Check the setting values displayed, modify them if necessary, and then press the Save button.

Name		Value
Incoming Mail Server (POP)	User Name	Your mail address
	Password	Your mail password
	Host Name	popssl.att.ne.jp
	Port	995
	Use TLS/SSL	Checked
	Authentication	Password
Outgoing Mail Server(SMTP)	User Name	Your mail address
	Password	Your mail password
	Host Name	smtssl.att.ne.jp
	Port	465
	Use TLS/SSL	Checked
	Authentication	MD5 Challenge-Response

Account Information | Mailbox Behaviors | **Server Settings**

Incoming Mail Server (POP)

User Name: xxx99999@xxxxx.att.ne.jp

Password: ●●●●●●

Host Name: popssl.att.ne.jp

Automatically manage connection settings

Port: 995 Use TLS/SSL

Authentication: Password

Advanced POP Settings

Outgoing Mail Server (SMTP)

Account: xxxxx.att.ne.jp

User Name: xxx99999@xxxxx.att.ne.jp

Password: ●●●●●●

Host Name: smtssl.att.ne.jp


Automatically manage connection settings

Port: 465 Use TLS/SSL

Authentication: MD5 Challenge-Response

Save


Step11. Open the "Account" pull-down menu under "Outgoing Mail Server (SMTP)" and click "Edit SMTP Server List".




- Step12.**
- ① Select “Accounts” on the list.
 - ② Check the following list.
 - ③ Click ”OK”.

Name		Value
Outgoing Mail Server (SMTP)	Description	e.g. SpinNet_SendSetting
	User Name	Your mail address ※Please be careful not to misplace your account.

Step13. Make sure that the “Account” pull-down menu under “Outgoing Mail Server (SMTP)” has the same name as the “Description” set in Step 12.



Step14. If the following window appears, click "Save" to close it.



This concludes the settings.